



5) Double-click the “Device Manager” and you see a list of all your PC’s devices.




6) In the Device Manager, under Ports (COM & LPT), you should see the **Prolific USB-to-Serial Comm Port (COMx)** device. (Note: There may be a yellow exclamation point to the right of this device). Right click on this and select “**Update Driver Software**”.

7) Select “**Browse my computer for driver software**”.





8) On the next screen, select “**Let me pick from a list of device drivers on my computer**”.



9) On the next screen, you should see a list of cable drivers. Be sure to select the driver:

Prolific USB-to-Serial Comm Port Version: 3.4.25.218 [10/7/2011].

Highlight this driver and click <Next> You should see a quick progress bar and then a screen that reads “Windows has successfully updated your driver software. Click Close.



If you return to Device Manager, you should not see a yellow exclamation mark next to the device under Ports (COM & LPT). This indicates that the cable driver has been successfully installed.